

## CAPL Scripting Quickstart


CAPL (Communication Access Programming Language) For CANalyzer and CANoe

# Agenda

► <b>Important information before getting started</b>	<b>3</b>
Visual Sequencer (GUI based programming (Subset of CAPL))	7
Brief Introduction to CAPL	11
Notes on Panel creation and use	24
Where to find additional information	28
Contact Information	30

## CANalyzer versus CANoe


**CANalyzer is wholly contained within CANoe**



CANoe offers significant additional capability beyond CANalyzer to:

- > Stimulate the network(s) with **Interaction Layer** knowledge
- > Run automated tests and generate test reports
- > Implement automated diagnostic tests

## CANoe and the added value of the Interaction Layer



- ▶ The CANoe Interaction Layer (in short CANoeIL):
  - > Provides a signal-oriented means of accessing the bus
  - > Map signals to their appropriate send messages
  - > Controls the sending of these messages as a function of the (OEM) Send Model
- ▶ Transmission of messages and signals is described based on attributes in the database
- ▶ CANoeIL models the transmission behavior at run-time using those attributes

## Overview of CANalyzer variants

### **CAPL is available in CANalyzer PRO and all versions of CANoe**

CANalyzer is available in three different variants:

- ▶ PRO: Professional variant: full functionality
- ▶ EXP: Expert variant: supports all applications up to complex analysis of heterogeneous systems; does not support CAPL programs
- ▶ FUN: Fundamental variant: simple applications, does not support CAPL, diagnostic tester and panels

Detailed information about the variants of CANalyzer is available at our website: [http://www.vector.com/vi\\_canalyzer\\_variants\\_en.html](http://www.vector.com/vi_canalyzer_variants_en.html)

# Agenda

Important information before getting started	3
► <b>Visual Sequencer (GUI based programming (Subset of CAPL))</b>	<b>7</b>
Brief Introduction to CAPL	11
Notes on Panel creation and use	24
Where to find additional information	28
Contact Information	30

## General

Available in both CANalyzer PRO and EXP

- > Intended to allow some automation within the EXP variant

The Visual Sequencer allows you to create *automated command sequences* with the purpose of

- > Stimulating the network
- > Controlling applications


In order to *structure* the individual steps, loops and conditional command blocks can be used, such as

- > `if, else if, end if`

Each sequence is shown in a *separate window*, and can be edited at any time, even while a measurement is running.

## Features


- ▶ Send messages (cyclically)
- ▶ Set signals/variables
- ▶ If, else, else if and repeat commands
- ▶ Wait commands
- ▶ Start/stop replay
- ▶ Write text or values to write window or file
- ▶ Graphical debug
- ▶ Auto complete for names





Visual Sequencer (GUI based programming (Subset of CAPL))

See the CANsystemdemo.cfg included with your installation



# Agenda

Important information before getting started	3
Visual Sequencer (GUI based programming (Subset of CAPL))	7
► <b>Brief Introduction to CAPL</b>	<b>11</b>
Notes on Panel creation and use	24
Where to find additional information	28
Contact Information	30

## General

Functional blocks based on CAPL (Communication Access Programming Language) can be created to program

- ▶ Network node modules
- ▶ Special evaluation programs for individual applications


Some CAPL characteristics:

- ▶ C-like programming language
- ▶ **Event based**, not interrupt driven
- ▶ CAPL programs are created using an integrated development environment called the CAPL Browser
- ▶ Direct access to signals, system variables and diagnostic parameters
- ▶ Able to link user created DLLs


## Field of Application CANoe

- ▶ Creating and extending simulations
- ▶ Implementing functions for analysis in the measurement setup

### Simulation Setup




### Measurement Setup




## Field of Application CANalyzer

- ▶ Creating simulations or reactive scripts
- ▶ Implementing functions for analysis in the measurement setup


### Send Loop of the Measurement Setup



### Analysis Branches




## CAPL Browser




## Compiling

- In order to generate an executable program file from a CAPL program, the program must be compiled with the CAPL compiler:



- Error messages are shown in the lower Message Window:



When you double-click the error description, the cursor in the *Text Editor* automatically jumps to the point in the source code, where the error originated.

## Examining a CAPL program

```
1  /*@!Encoding:1252*/
2  □ includes
3  {
4      // Include files are referenced here
5      #include "D:\Sandbox\Demo\CAPL\TxFilter.can"
6  }
7
8  □ variables
9  {
10     // Global Variables are defined here
11     int i;
12     char nameArray[255];
13 }
14
15 □ on key 'A'
16 {
17     int j;
18     j = 25;
19
20     write("The value of j is %d", j);
21 }
22 }
23
24 □ void myFunction(int input1, int input2)
25 {
26     // Your function code goes here
27 }
```

Additional CAPL files that contain generic code that can be reused in other programs


Variables defined here are accessible throughout the CAPL program

Multiple pre-defined event handlers exist for your use within CAPL. The code in this handler will only be executed when the event occurs.

You can create your own functions (special handler) that contain related code to be executed frequently




## Adding an Event Handler



CAPL is a procedural language in which the execution of program blocks is controlled by events. These program blocks are referred to as event procedures.


## Important Event Handlers

► Start of measurement



```
on Start
{
    write ("Start of CANoe");
}
```

► Message received



```
on message 0x123
{
    write ("CAN Message 123");
}
```

► Signal change



```
on signal sigTemp
{
    write ("Signal Temperature");
}
```

► Time event



```
on timer tmrCycle
{
    write ("within cycle");
}
```

► Key press



```
on key 'a'
{
    write ("Key >a< pressed");
}
```

## On Key Procedures

```
on key 'a'           // React to press of 'a' key
on key ' '           // React to press of spacebar
on key 0x20           // React to press of spacebar
on key F1            // React to press of F1 key
on key ctrlF12       // React to press of Ctrl-F12
on key PageUp        // React to press of Page Up key
on key Home          // React to press of Home key
on key *             // React to any key press except...
```

## Data types for CAN

Type		Name	Bit	Note
Integers	Signed	<code>int</code>	16	
		<code>long</code>	32	
		<code>int64</code>	64	
	Unsigned	<code>byte</code>	8	
		<code>word</code>	16	
		<code>dword</code>	32	
		<code>qword</code>	64	
Floating point		<code>float</code>	64	Per IEEE
		<code>double</code>	64	Per IEEE
Single character		<code>char</code>	8	
Message variable	for CAN	<code>message</code>		for CAN messages
Time variables	for seconds	<code>timer</code>		for Timer in s
	for milliseconds	<code>mstimer</code>		for Timer in ms


## Variables in CAPL

► CAPL code:

```
int i = 100;           // Declaration and initialization of an integer
char ch = 'a';         // Declaration and initialization of a character
float x;               // Declaration of a floating point number
```

```
write ("Hundred as decimal number: %d", i);
write ("Hundred as hexadecimal number: %x", i);
write ("Pi as floating point number: %f", pi);
write ("The decimal ASCII code of %c is %d", ch, ch);
write ("The value of x is %f", x);
```

► Results:



## Operators


Operator	Description	Example
+ -	Addition, subtraction	-
* /	Multiplication, division	-
++ --	Increment or decrement by 1	<code>a++; // increments a by 1</code>
%	Modulo division (returns integer remainder of a division)	<code>a = 4 % 3; // a is 1</code>
< <=	Less than; less than or equal to	returns TRUE or FALSE
> >=	Greater than; greater than or equal to	returns TRUE or FALSE
== !=	Compare for equality or inequality	returns TRUE or FALSE
&&	Logic AND	returns TRUE or FALSE
	Logic OR	returns TRUE or FALSE
!	Logic NOT	changes TRUE to FALSE and vice versa
&	Bitwise AND	<code>1 &amp; 7 // yields 1 (0001 &amp; 0111 → 0001)</code>
	Bitwise OR	<code>1   7 // yields 7 (0001   0111 → 0111)</code>
~	Bitwise complement	<code>~1 // yields 14 (0001 → 1110)</code>
^	Bitwise exclusive OR (XOR)	<code>01^11 // ergibt 10</code>
>> <<	Bit shift to right or left	<code>1 &lt;&lt; 3 // yields 8 (0001 → 1000)</code>

## Agenda

Important information before getting started	3
Visual Sequencer (GUI based programming (Subset of CAPL))	7
Brief Introduction to CAPL	11
► <b>Notes on Panel creation and use</b>	<b>24</b>
Where to find additional information	28
Contact Information	30

## Creating a Panel


A signal is mapped to each display or control:





## Creating a System Variable for use with in a configuration

Signals can be automatically or user created, saved, exported, and imported via the Configuration|Systems Variables dialog:



## Agenda


Important information before getting started	3
Visual Sequencer (GUI based programming (Subset of CAPL))	7
Brief Introduction to CAPL	11
Notes on Panel creation and use	24
► <b>Where to find additional information</b>	<b>28</b>
Contact Information	30

## Agenda

Important information before getting started	3
Visual Sequencer (GUI based programming (Subset of CAPL))	7
Brief Introduction to CAPL	11
Notes on Panel creation and use	24
► <b>Where to find additional information</b>	<b>28</b>
Contact Information	30

Where to find additional information

# Online Help file: Use Index|CAPL Introduction



The screenshot displays the Vector CANoe & Modules Online Help interface. On the left is a navigation pane with a search bar and a list of topics. The main content area is titled "CAPL Introduction" and is divided into several sections:

- Screenshot:** Shows a CAPL code snippet:

```
on start
{
  // net-management
  // set to 2 to get more information
  setWriteDbgLevel(1);
  writeDbgLevel(2,gECU);
}
```
- Quick Access:** Includes links to the **Glossary**, **CAPL Browser**, and **Technical Reference: CAPL Functions**.
- CAPL Basics:** Contains a list of topics including CAPL, Keywords, Instructions, Macros, Autocomplete, Classes, Arrays, Structures, Enumeration types, Associative fields, Messages, Selectors, and Linking a Windows DLL in CAPL.
- Procedures:** Includes sections for **Compile a CAPL Program** and **Working with Databases**.
- Diagnostics:** Contains links for **Usage of diagnostic objects in CAPL** and **Filter diagnostic objects using CAPL filter in the Measurement Setup**.
- Test:** Includes links for **Test Service Library: CAPL test modules**, **Test Service Library: CAPL simulation nodes**, and **Constraints and conditions (CAPL)**.
- FlexRay:** Contains a link for **Usage of CAPL functions**.
- Structure of a CAPL Program:** Includes sections for **Variables**, **Include Files**, **Event Procedures**, and **Functions**.
- Direct Access to Values/Signals in CAPL:** Includes links for **Direct access to values from system variables** and **Direct access to values from environment variables**.
- Direct Access to Signals:** Includes links for **Concept of a signal in CAPL**, **Signal qualification for signal ambiguity**, **Reading signal values (raw or physical value)**, **Setting signal values**, **Response to signal changes**, **Signals as functions parameters**, and **Heuristics for signal identification**.

## Agenda

Important information before getting started	3
Visual Sequencer (GUI based programming (Subset of CAPL))	7
Brief Introduction to CAPL	11
Notes on Panel creation and use	24
Where to find additional information	28
► <b>Contact Information</b>	<b>30</b>

## Looking for more information?

Visit our website:

> <http://www.vector.com>

Sign in for a Vector training class:

> [http://www.vector.com/vi\\_training\\_en.html](http://www.vector.com/vi_training_en.html)

*Need help with Vector tools?*

Contact our support team:

> (248) 449 – 9290 Option 2

> [support@us.vector.com](mailto:support@us.vector.com)